

Tech Info Library

A/UX: How to Make an NFS File System Mount Automatically (9/94)

Revised: Security:	
A/UX: How to Ma	ke an NFS File System Mount Automatically (9/94)
=========	
Article Created: 15 October 1990 Article Reviewed/Updated: 6 September 1994	
TOPIC	
My NFS file systems aren't mounting automatically.	
DISCUSSION	
Usually, one of two things cause this. The first is that the NFS entry	

Usually, one of two things cause this. The first is that the NFS entry in /etc/fstab is incorrect. To check this, follow these steps:

- 1) Log on as "root".
- 2) Edit the file /etc/fstab. This file lists all of the partitions which should be automatically mounted when the system is booted into multi-user mode.
- 3) As needed, add an entry for each NFS partition that you would like mounted automatically. The format needed is displayed in /etc/fstab:

rhost_1 is the name of the repote host. "filename" is the file system to be mounted. /mnt is the mount point, the directory to which the file system will be attached.

The other reason is that NFS file systems are mounted at startup only if the appropriate line has been altered in /etc/inittab. To see if yours is correct, follow these steps:

- 1) Log on as "root".
- 2) Enter the command:

grep mount /etc/inittab

You should see:

nfs8:2:once:/etc/mount -at nfs > /dev/syscon 2>&1

If this is not displayed, do these steps:

- 1) Edit the file /etc/inittab
- 2) Change the line

```
nfs8:2:off:/etc/mount -at nfs > /dev/syscon 2>&1
```

to

nfs8:2:once:/etc/mount -at nfs > /dev/syscon 2>&1

- 3) Save the file and quit the editor.
- 4) Shut the system down into single-user mode.
- 5) Bring the system back up into multi-user mode. The system will display the names of the local and NFS partitions as they are mounted.

The other reason that this happens is because you are in single-user mode. To find your run level, type

who -r

This should be displayed:

```
run-level 2 Apr 14 09:59 2 0 S
```

The number in the second column of the output should be a "2".

If it is an "S", your system is in single-user mode and must be booted into multi-user mode. To boot into multi-user mode:

1) Enter the command:

init 2

This will start the system booting into multi-user mode. During the booting process, it will ask if you'd like "the rest of the partitions" checked by fsck.

2) Press "Y" and Return.

When the system is up in multi-user mode:

- 1) Log on as "root".
- 2) Enter the command: df

..TIL06527-A-UX-How_to_Make_an_NFS_File_System_Mount_Automatically_9-94_(TA45043).p

The output will list all currently-mounted partitions, both local and remote.

Article Change History: 06 Sep 1994 - Reviewed. 31 Aug 1992 - Reviewed.

Support Information Services

Copyright 1990-94 Apple Computer, Inc.

Tech Info Library Article Number:6527