



# Tech Info Library

## PowerTalk: Mail\*Link QuickMail to PowerTalk Read Me File (10/95)

Revised: 10/19/95  
Security: Everyone

PowerTalk: Mail\*Link QuickMail to PowerTalk Read Me File (10/95)

=====  
Article Created: 18 October 1995

TOPIC -----

This article contains the ReadMe file included with the Mail\*Link for PowerTalk/QM gateway software posted online.

DISCUSSION -----

Mail\*Link for PowerTalk/QM 1.6

This is a personal gateway for PowerTalk users. This gateway will allow PowerTalk users to send and receive mail from their QuickMail accounts without having to login to QuickMail and use the QuickMail DA. Mail can be sent and read with your favorite PowerTalk mail enabled application.

This release of Mail\*Link for PowerTalk/QM is the first release of this gateway by Apple Computer Inc. This gateway is functionally equivalent to version 1.0.5. Future versions of this software will be modified and enhanced.

This software is licensed to you under the Macintosh System 7.5 license agreement. All terms and conditions of this license must be followed.

Note: If you are upgrading from version 1.0.5 or earlier it is VERY IMPORTANT that you follow the instructions in the Upgrading Section below.

The installation and upgrade procedure for this software will still install the StarNine demonstration key files (which were part of the 1.0.5 release). However the 1.6 release of the gateway has been modified to ignore the key files and thus will never expire.

INSTALLATION INSTRUCTIONS

=====  
For new installations only:

We recommend that you install this software via the installer script.

Step 1

-----

Double click on either the "Installer" icons.

Step 2

-----

Select the drive on which you wish to install this software.

Step 3

-----

Reboot the system after the software has been properly installed.

UPGRADE INSTRUCTIONS

=====

If you are upgrading from a previous release of Mail\*Link PT/QM, you should follow these instructions:

Step 1

-----

Install the software as instructed in the section "INSTALLATION INSTRUCTIONS".

Step 2

-----

After the system has rebooted, open the "PowerTalk Key Chain".

Step 3

-----

Open the QuickMail personal gateway in the key chain. The installation procedures change the file-id that PowerTalk uses to locate the Mail\*Link PT/QM file. Opening and closing the QuickMail Service configuration window will cause the new file-id to be written into the PowerTalk configuration file.

Step 4

-----

Close the key chain. You will be told that you must reboot the system before PowerTalk will activate the gateway.

Step 5

-----

Reboot the system.

If you have trouble with the gateway after upgrading please re-install by following the instructions in the Clean Upgrade Install section below.

CONFIGURATION

=====

Creating your QuickMail personal gateway

-----

Once you have installed the software and rebooted the system (as described

above), follow these instructions to create your QuickMail personal gateway.

Step 1

-----

Open the "Key Chain" located on your desktop.

Step 2

-----

Press the "Add" button.

Step 3

-----

You will be presented with a list of services that are available. Select "QuickMail".

Step 4

-----

A new item with the server name of "Not Configured" and a service type of "QuickMail" will appear in your "Key Chain".

Step 5

-----

Proceed to the "Configuring" section below.

Configuring your QuickMail personal gateway

-----

To configure the QuickMail personal gateway, ensure that the "Key Chain" has been opened.

Step 1

-----

You first need to select your QuickMail directory service. To do this: open the Chooser, choose QuickMessenger, select the directory service and close the Chooser.

Step 2

-----

Double click (Open) the item with a service type of "QuickMail". The QuickMail personal gateway only allows one instantiation, so there should only be one item with this type in the Key Chain window.

Step 3

-----

A configuration window will be displayed. You should configure each item in this window before closing the window. Window closing is equivalent to pressing the "OK" button in a dialog. The "Key Chain" configuration windows have no "Cancel" operation, so please ensure each item is properly filled in before closing the window (you can always come back and change the selections at a later date, but it is better if each item is properly filled in).

Step 4

-----

Once you have entered the information in the configuration window, close the window with a mouse click in the close box or by typing "<command>W". It may take a few seconds for the window to close. This is because PowerTalk is activating all of the personal gateway subsystems and informing them of their new configuration. Be patient.

Step 5

-----  
Once the QuickMail configuration window is closed, close the Key Chain window.

CLEAN UPGRADE INSTALLATION

=====

Use this procedure if you are experiencing problems with the gateway software. You should not need to use this procedure for normal installs. To perform a "Clean Install" of the gateway software, use the following procedure.

NOTE: Some gateways may remove mail from your In Tray and Out Tray when they are reinstalled. Be sure to back up any items in your InTray and OutTray by dragging them to another folder on your hard drive.

NOTE: This will remove all services from your keychain, so be sure you have the passwords for these services handy. If you have personal gateways already installed, you will need to set them up again, so be sure you write down the setup information that is contained in each key, if necessary.

This procedure removes all "Mail\*Link" gateways. If you have multiple "Mail\*Link" gateways installed, you will need to re-install each of the gateways you want to use.

Step 1

-----  
Open the Extensions folder, located inside the System Folder. Find the following item(s) and drag to the trash (note only the gateways you have installed will be in the Extensions folder):

- Mail\*Link PT/QM
- Mail\*Link PT/MS
- Mail\*Link PT/INET

Step 2

-----  
Open the Preferences folder, located inside your System Folder. Find the following items and drag them to the trash.

- StarNine (folder)
- PowerTalk Setup Preferences
- PowerTalk Startup Preferences

Step 3

-----  
Find the "Mail\*Link Extras" folder, on the top level of your hard drive. Drag this folder to the trash.

Step 4

-----

Restart your machine. After you have restarted, choose "Empty Trash" from the Special menu.

Step 5

-----

Double-click the installer for the desired software, and click Install at the Easy Install screen. After the installation is complete, your machine will restart. If you are installing more than one gateway, repeat this step for each gateway.

Step 6

-----

Open the keychain and click "Add". Select the gateway from the list of choices. A new item will be added to the Key Chain. Open this key, and configure the gateway as you normally would. The gateway should now be functioning.

#### MANUAL INSTALLATION INSTRUCTIONS

=====

The manual installation instructions are for advanced users who wish to build their own installation process or who wish to install only portions of this gateway. Installation using this process should be conducted only after you fully understand how to use your Macintosh, and how to configure and use PowerTalk gateways.

If you must install this version manually, please follow these instructions:

Step 1

-----

Place the distribution diskette in the floppy drive.

Step 2

-----

Open the folder named "Drop Contents on System Folder".

Step 3

-----

Select all of the items in this folder and drag them onto the "System Folder" icon.

Step 4

-----

You will be presented with a dialog box that indicates these files belong in special locations. Click "OK".

Step 5

-----

Close the "Drop Contents on System Folder" folder.

Step 6

-----

Open the folder named "Place Contents in Preferences Folder".

Step 7

-----

Select all of the items in this folder and drag them into the "Preferences" folder (which is located within your "System Folder").

Step 8

-----

If you are presented with a dialog indicating that you will be replacing existing files, click cancel. You should perform the "Automatic Installation" procedure (above).

Step 9

-----

Reboot the system. This is necessary because some of the software installed is only activated at boot time.

Note: With version 1.6 it is no longer required to install the key files.

KNOWN INCOMPATIBILITIES

=====

- When forwarding a mail message, the name and address of the original sender of the message is not preserved.
- When forwarding a message, the form content of the forwarded message is lost unless you type at least 1 character into the forwarded message.

SUPPORT

=====

If you need any additional help installing, configuring or using this gateway please call Apple Support at: 1 (800) SOS - APPL

(10/10/95)

1993 StarNine Technologies, Inc., All rights reserved

Support Information Services

Copyright 1995, Apple Computer, Inc.

Tech Info Library Article Number:18778