

Tech Info Library

Newton Connection Kit 2.0: How to Switch from 1.0 (10/94)

Revised: 10/12/94 Security: Everyone

Newton Connection Kit 2.0: How to Switch from 1.0 (10/94)

Article Created: 6 July 1994

Article Reviewed/Updated: 12 October 1994

TOPIC -----

This article explains how to switch from Newton Connection Kit 1.0 to version 2.0

DISCUSSION -----

Synchronized files created with Newton Connection 1.0 are incompatible with Newton Connection 2.0 and vice-versa. This means you cannot use Newton Connection 2.0 to synchronize or restore from a Newton Connection 1.0 file. Therefore, BEFORE using Newton Connection 2.0, perform the following steps:

- 1. Launch Newton Connection 1.0.
- 2. Synchronize. This makes sure your Newton (and PCMCIA card if applicable) contains all the information you may have added to the 1.0 synchronize file since the last synchronization.
- 3. Quit Newton Connection 1.0 and delete or rename (see NOTE) the 1.0 synchronization file. This ensures that Newton Connection 2.0 does not try to use the 1.0 file when synchronizing.
- 4. If you have not already done so, install Newton Connection 2.0.
- 5. Launch Newton Connection 2.0 and synchronize. This creates a new 2.0 synchronization file with the data currently in your Newton.

NOTE: Once you are comfortable using the new version, we suggest you delete the old 1.0 files. If you do decide to keep any 1.0 files around, please keep a copy of Newton Connection 1.0 around. If you accidentally restore a 1.0 file using Newton Connection 2.0, you will see a -48025 error when you try to synchronize.

Perform the following steps to correct this problem:

..TIL15752-Newton_Connection_Kit_2-0-How_to_Switch_from_1-0_10-94_(TA32040).pdf

- 1. Quit Newton Connection 2.0.
- 2. Launch Newton Connection 1.0.
- 3. Using Newton Connection 1.0, restore the 1.0 synchronize file onto Newton.
- 4. Quit Newton Connection 1.0.
- 5. Delete the old 2.0 synchronize files.
- 6. Launch Newton Connection 2.0.
- 7. Synchronize using Newton Connection 2.0.

Everything is now ready to go.

Article Change History:

12 Oct 1994 - Added keyword and made minor formatting changes.

Support Information Services

Copyright 1994, Apple Computer, Inc.

Tech Info Library Article Number:15752