

Tech Info Library

Pascal: Intrinsic unit for Silentype procedures (1 of 3)

Revised: 12/5/84
Security: Everyone

Pascal: Intrinsic unit for Silentype procedures (1 of 3)

Appendix D (pp. 53-59) of the Silentype reference manual indicates that all parameter procedures can be placed into an intrinsic library unit. This is a handy and valuable unit to have if you plan to use the Silentype printer in a Pascal program.

To extend the usefulness of the Silentype unit, two procedures have been added to this listing and another has been changed. These three procedures are discussed here; refer to the Silentype manual for a description of the remainder.

Procedure SetPage (Page: integer):

This procedure allows you to change from one high-resolution graphics screen to the other; however, only the first high-res page is used in the Pascal system. Values: 1=first page; 2=second page.

Procedure ColdStart:

The ColdStart procedure resets the Silentype parameters to the default values as specified in the printer manual. This procedure is equivalent to turning off the power to the printer.

Values: none required.

Procedure WarmStart:

The Restore procedure as listed in the Silentype manual has been revised and renamed WarmStart. Included in the revision is the SetPage procedure. This procedure differs from ColdStart in that the parameters set by WarmStart are user-definable; that is, they reflect the particular setup that you find most appliable to your needs. For instance, you may set a darkness setting to 3 or 5, and so on.

Initialization Code:

The initialization code consists of a call to the ColdStart procedure. This call is executed when the unit is first brought into the system from the

..TIL00683-Pascal-Intrinsic_unit_for_Silentype_procedures_1_of_3_(TA45259).pdf

library to ensure that the printer is not retaining any settings from previous uses with either Pascal or BASIC. If you wish, you may change this code to WarmStart or another code of your choice; you may also leave the initialization section empty, though in that case you should still include the BEGIN and END.

Installing the Unit:

The Silentype unit comes ready for you to enter it, compile it and install it in your copy of SYSTEM.LIBRARY, though you may wish first to change the Intrinsic Code value or the contents of WarmStart to suit your individual needs. Refer to pp. 186-193 of the Apple Pascal Operating System Reference manual for the instructions for placing the compiled Silentype unit into your SYSTEM.LIBRARY.

```
(*$S+*)
Unit Silentype; Intrinsic Code 27;
Interface
  Procedure ROMEnable;
  Procedure SetByteValue (Loc, Value: integer);
  Function ByteValue (LOC: integer): integer;
  Procedure Send (CH: CHAR);
  Procedure SetUniDirect;
  Procedure SetBidirect;
  Function UniDirect: boolean;
  Procedure SetNegative;
  Procedure SetPositive;
  Function Negative: boolean;
  Procedure SetPage (Page: integer);
  Procedure SetDark (Darkness: integer);
  Function Dark: integer;
  Procedure SetForm (Length: integer);
  Function Form: integer;
  Procedure SetSpace (Length: integer);
  Function Space: integer;
  Function LeftMargin: integer;
  Function RightMargin: integer;
  Procedure SetLeftMargin (Position: integer);
  Procedure SetRightMargin (Position: integer);
  Procedure PrintBuffer;
  Procedure ClearBuffer;
  Procedure FormFeed;
  Procedure PrintPic;
  Procedure ColdStart;
  Procedure WarmStart;
```

Apple Tech Notes

Tech Info Library Article Number:683